



# Upgrade Guide

Forcepoint DLP

**v8.8.1**

©2021 Forcepoint

Forcepoint and the FORCEPOINT logo are trademarks of Forcepoint. All other trademarks used in this document are the property of their respective owners.

Published 2021

Every effort has been made to ensure the accuracy of this document. However, Forcepoint makes no warranties with respect to this documentation and disclaims any implied warranties of merchantability and fitness for a particular purpose. Forcepoint shall not be liable for any error or for incidental or consequential damages in connection with the furnishing, performance, or use of this manual or the examples herein. The information in this documentation is subject to change without notice.

Document last updated March 24, 2021

# Contents

<b>Chapter 1</b>	<b>Preparing to Upgrade to Forcepoint DLP v8.8.1</b>	<b>1</b>
	Prepare for upgrade	1
	Download and launch the installer	2
<b>Chapter 2</b>	<b>Upgrading Forcepoint DLP</b>	<b>5</b>
	Upgrade the management infrastructure	5
	Upgrade data security components on the management server	6
	Complete post-upgrade steps on the management server	7
	Upgrade supplemental servers and Windows-based agents	8
	Upgrade protectors	8
	Preparing to upgrade the protector	8
	Upgrading the protector	9
	Upgrade the Forcepoint DLP Protector software	9
	Deploy settings	10
	Reconfigure Risk-Adaptive Protection in Forcepoint DLP	10
	Data Protection Service	10
	Configuring Data Protection Service	11
	Re-enabling fingerprint classifiers	12



# 1

## Preparing to Upgrade to Forcepoint DLP v8.8.1

The existing Forcepoint DLP installation must be at one of the following versions to upgrade to version 8.8.1:

- 8.8
- 8.7.x
- 8.6.0
- 8.5.x

If you have an earlier version, you will need to upgrade to version 8.5 first before beginning your upgrade to 8.8.1

The existing data security solution must be at least version 8.5.x to upgrade directly to Forcepoint DLP version 8.8.1. Those currently using an earlier version must perform interim steps, as shown in the table below:

Current version	Step 1	Step 2
8.0.x, 8.4.x	Upgrade to 8.5	Upgrade to 8.8.1
8.5–8.8	Upgrade to 8.8.1	

To get started, see:

1. [Prepare for upgrade](#)
2. [Download and launch the installer](#)

## Prepare for upgrade

To ensure a successful upgrade:

1. Unless instructed otherwise by Forcepoint Technical Support, make sure the system is functional prior to upgrade.
2. Verify that the starting version is 8.5.x, 8.6.x, 8.7.x, or 8.8.

3. Perform a full backup of the system (including both product and infrastructure backups, as described in the appropriate version of the [Backup and Restore FAQ](#)).
4. If fingerprinting tasks are running, stop the fingerprinting and disable the scheduler.
5. Route all traffic away from the system.
6. Ensure that any supplemental fingerprint repositories are fully synchronized with the primary repository. Check for synchronization in the system log.
7. Log on to the management console to make sure all settings are deployed successfully. (If the **Deploy** button is highlighted, click it.)
8. If the existing deployment includes Forcepoint-supplied custom file types, change the name of the following configuration files as follows:
  - a. Navigate to the `\policies_store\custom_policies\config_files` subdirectory under the installation directory for your product.
  - b. Rename “extractor.config.xml” to **custom\_extractor.config.xml**.
  - c. Rename “extractorlinux.config.xml” to **custom\_extractorlinux.config.xml**.The file names are case-sensitive.
9. If administrators have removed applications from the product’s predefined endpoint application groups, make a list of the changes. Application groups are restored after upgrade, the applications will need to be removed again. Custom user-defined groups are unaffected.
10. Disable User Account Control (UAC) and Data Execution Prevention (DEP) settings, and make sure that no Software Restriction Policies will block the installation. The UAC settings can be re-enabled following the upgrade.

The speed and success of the upgrade process are affected by many factors, including:

- Number of online incidents
- Size of the forensics folder
- Number of policies or rules in use
- User directory import size
- Whether GPO restrictions are enforced on the server in domain membership scenarios
- Hardware specification

## Download and launch the installer

---

The Forcepoint Security Installer (ForcepointDLP88Setup.exe) is used to upgrade the management server and other Windows-based servers.

The management server is always upgraded first.

To download the installer onto the management server machine:

1. Navigate to [support.forcepoint.com](https://support.forcepoint.com) and click the **My Account** link.
2. Log in, click **Downloads** in the menu bar at the top of the page, then click the **All Downloads** link.
3. Under **Data Security > Forcepoint DLP**, click the **8.8.1** link.
4. Select **Forcepoint DLP** in the list of installers.
5. On the Product Installer page, click the **Download** link near the bottom of the page.
6. When the installer has downloaded successfully, double-click the file to launch the installer.

It may take several minutes for the installer to unpack files and launch. This is expected behavior.

The installation package detects that earlier versions of the product are installed, and automatically starts a series of wizards.

After upgrade, the system has the same configuration as before the upgrade. The upgrade process does not allow the option to change configuration or settings.





# 2

## Upgrading Forcepoint DLP

Perform the upgrade steps in the order described.

Start the upgrade process by upgrading the management server. This is critical, because if supplemental servers or agents are upgraded before the management server, they stop communicating. When the management server is upgraded first, it continues communicating with the components until they are upgraded.

1. [Upgrade the management infrastructure, page 5.](#)
2. [Upgrade data security components on the management server, page 6.](#)
3. [Complete post-upgrade steps on the management server, page 7.](#)
4. After upgrading the management server, upgrade supplemental servers and any other server components:
  - [Upgrade supplemental servers and Windows-based agents, page 8.](#)
  - [Upgrade protectors, page 8.](#)
  - [Upgrade the Forcepoint DLP Protector software, page 9.](#)
5. After upgrading the management server and other server components, it is essential to deploy changes (see [Deploy settings, page 10](#)).
6. Next, in deployments that include endpoint software, [Reconfigure Risk-Adaptive Protection in Forcepoint DLP, page 10](#).
7. If you have a DLP Cloud Applications license and are not already connected to Data Protection Service, see [Data Protection Service, page 10](#) before upgrading.
8. If you are using Dynamic Data Protection (Endpoint DLP and Forcepoint Behavioral Analytics), you need to download the RAP User Manager tool to enable users for Dynamic Data Protection on a DLP system. See the [DDP Getting Started Guide](#) for more information.

### Upgrade the management infrastructure

---

The Forcepoint Infrastructure provides basic framework for all of the components that make up management server. This framework includes a central settings database that stores shared configuration (like administrator directory and account information) for all management modules, as well as other internal shared services.

The infrastructure upgrade wizard contains the following screens.

Wizard Screen	Fields
Welcome	Initiates the wizard. <ol style="list-style-type: none"><li>1. Click <b>Next</b> to begin the upgrade process. The system checks disk space requirements.</li><li>2. When prompted, click <b>Next</b> to launch the installation wizard.</li></ol>
Pre-Installation Summary	Shows information about the upgrade, including: <ul style="list-style-type: none"><li>• The destination folder for the installation files</li><li>• The name of the SQL Server machine and the user name of an authorized database administrator</li><li>• The IP address of the management server and its administrator credentials</li></ul> Click <b>Next</b> to accept the properties.
Installation	Shows upgrade progress. The system stops processes, copies new files, updates component registration, removes unused files, and more. A popup message appears at this stage, warning that all modules must be upgraded. This popup may be hidden behind the main installer window, so if the upgrade process appears to freeze, locate the hidden popup by moving the main installer window, then click <b>OK</b> to proceed. In addition, if a Data Task Scheduler window opens, the installer offers the option to stop the Work Scheduler service, or continue running the installer and reboot at the end. Reboot is the recommended approach.
Summary	Provides an overview of what has been upgraded, including: <ul style="list-style-type: none"><li>• The destination folder for the installation files</li><li>• The name of the SQL Server machine and the user name of an authorized database administrator</li><li>• The IP address of the management server and its administrator credentials</li></ul> Click <b>Finish</b> to complete the upgrade for this module. Restart the machine if prompted.

## Upgrade data security components on the management server

---

Before running the Forcepoint DLP upgrade wizard, the installer validates system requirements to ensure the upgrade will be successful.

The pre-upgrade check validates hardware requirements, credentials for the SQL Server management database, endpoint security certificates, manager configuration,

administrator upgrade permissions, and the database structure. As it proceeds, it reports whether a step succeeded or failed, or it shows a warning.

- If there is a failure, the upgrade stops. For details, see **\TRITON-PreUpgrade-SystemTests.log** in the product's installation directory.
- If there are only warnings, the installer offers the option to continue the upgrade. Continuing without repairing the issues may cause unexpected behavior, but should not a critical impact.
- If the pre-upgrade check succeeds, or if the administrator continues after viewing warnings, the Forcepoint DLP wizard is launched, followed by wizards for each installed component.

The Forcepoint DLP upgrade wizard contains the following screens.

Wizard Screen	Fields
Welcome	Initial Forcepoint DLP installation wizard launch page. The system checks the disk space on the machine. When prompted, click <b>Next</b> to launch the installation wizard.
Configuration	Step through the screens configured during the previous product installation, including Fingerprinting Database, Temporary File Location, and Local Administrator. Click <b>Next</b> on each to retain the existing settings.
Installation Confirmation	Review the settings on the Installation Confirmation screen and click <b>Install</b> to continue the upgrade.
Installation	Shows the progress of the installation. The system stops processes, checks ports, copies new files, updates component registration, removes unused files, and more. In certain circumstances, an internal SQL error may appear. If this occurs, do not click OK until the issue has been resolved with Forcepoint Technical Support. Continuing without resolving the issue can cause problems with the reporting database.
Summary	Summarizes the upgrade configuration. <ol style="list-style-type: none"> <li>1. Click <b>Done</b>. A prompt about updating predefined policies and content classifiers appears.</li> <li>2. Click <b>OK</b> to install the updates. The status of the updates is displayed, including the items being updated and details such as how many policies are updated, deleted, or added.</li> <li>3. Click <b>Close</b> when the updates are complete. Restart the computer, if prompted.</li> </ol>

## Complete post-upgrade steps on the management server

After the upgrade process has completed successfully:

1. Log on to the management server machine with Administrator permissions.
2. To re-register all other components to the management server, run the appropriate installer on each host machine (see [Upgrade supplemental servers and Windows-based agents](#), page 8).
3. Log into the Forcepoint Security Manager.
4. If applications were removed from the predefined endpoint application groups prior to upgrade, go to the **Main > Resources > Endpoint Application Groups** page and remove them again.
5. After upgrading all components, click **Deploy** in the Security Manager.

## Upgrade supplemental servers and Windows-based agents

---

To upgrade a supplemental Forcepoint DLP server, or a Windows-based standalone agent, to v8.8.1:

1. Launch the Forcepoint Security Installer, **Forcepoint Infrastructure**. The software is detected and the upgrade wizard appears.
2. Click **Next** until the wizard is completed.  
Forcepoint DLP components found on this machine from a supported previous version are upgraded.
3. Finishing the upgrade process requires deploying changes in the Forcepoint Security Manager. As a best practice, finish upgrading all components, then log into the Forcepoint Security Manager and deploy all of the changes at once.
4. Wait 30 minutes before routing traffic through the upgraded system.  
This allows the upgraded server time to download the information necessary for resolving source and destination resources such as people, computers, and printers. Routing traffic through the system before this is complete may cause:
  - Potential false positives and negatives
  - File-system discovery problems, where the discovery starts but immediately fails

## Upgrade protectors

---

Protectors can be upgraded from v8.4 and later.

### Preparing to upgrade the protector

Use these steps if the protector is at v8.4 or later.

To download the upgrade script on the protector machine:

1. Navigate to [support.forcepoint.com](https://support.forcepoint.com) and click the **My Account** link.
2. Log in, then click **Downloads** in the menu bar at the top of the page.
3. Under Data Security > Forcepoint DLP, click the **8.8.1** link.
4. Select **Forcepoint DLP Appliance Upgrade Script from 8.4, 8.5.x, 8.6, 8.7, 8.7.1, 8.7.2, 8.8 to 8.8.1** in the list of installers.
5. On the Product Installer page, click the **Download** link near the bottom of the page.
6. When the download is complete, unzip the **ProtectorUpdate881.zip** file.
7. Copy the resulting file, **protector-update-8.8.1-yyyy**, to directory **/tmp** directory. Here, *x-yyyy* is the latest version and build number, such as 8.8.1-3456.

## Upgrading the protector

To run the upgrade script:

1. Enter the following command:  

```
chmod +x /tmp/protector-update-8.8.1-yyyy
```
2. Enter the following command:  

```
bash /tmp/protector-update-8.8.1-yyyy
```
3. Answer **Y** on the “Are you sure?” question, and complete the wizard, accepting the defaults.
4. Restart the protector machine when the wizard completes.
5. Deploy changes to complete the upgrade process. See [Deploy settings, page 10](#).
6. Wait 30 minutes before routing traffic through the new system. It takes time for it to download the information necessary for resolving source and destination resources such as people, computers, and printers. Routing traffic through the system before this is complete may result in false positives and negatives.

## Upgrade the Forcepoint DLP Protector software

---

If your deployment includes the Forcepoint DLP Protector software package, the upgrade process differs slightly from that described in [Upgrade protectors, page 8](#). Use the following steps to upgrade the Protector software package.

1. To download the software protector installer:
  - a. Navigate to [support.forcepoint.com](https://support.forcepoint.com) and click the **My Account** link.
  - b. Log in, then click **Downloads** in the menu bar at the top of the page.
  - c. Under Data Security > Forcepoint DLP, click the **8.8.1** link.
  - d. Select **Forcepoint DLP Network appliance software package (Protector)** in the list of installers.
2. Log in to the installation machine as **root** and copy the installation file into the Protector’s **/tmp** directory.

3. Run the following command:

```
chmod +x /tmp/ForcepointDLP881ApplianceSoftwarePackage
```

4. Execute **ForcepointDLP881ApplianceSoftwarePackage**.
5. Complete the wizard.
6. Restart the Protector.

## Deploy settings

---

After upgrading all servers, agents, and appliances to Forcepoint DLP v8.8.1, deploy changes in the Forcepoint Security Manager. Endpoints do not require a separate deploy step.

1. Log into the Data Security module of the Forcepoint Security Manager.
2. When prompted to update policies, follow the on-screen instructions.  
Depending on the number of existing policies, this can take up to an hour. During this time, do not restart the server or any of the services.
3. Click **Deploy**.

## Reconfigure Risk-Adaptive Protection in Forcepoint DLP

---

If you upgrade from version 8.5.2 to 8.8.1, it is necessary to reconfigure your Risk-Adaptive Protection settings after the upgrade is complete. Use the following steps for the configuration.

1. Log on to the Data Security module of the Forcepoint Security Manager.
2. Go to the **General > Services > Risk-Adaptive Protection** page.
3. Mark the check box **Enable Risk-Adaptive Protection**.
4. Enter the Forcepoint Behavioral Analytics host name and port.
5. Click **Test Connection** to verify the connectivity with Forcepoint Behavioral Analytics.
6. Click **OK** to save your settings.
7. Click **Deploy**.
8. Restart Windows service: **Websense Data Security Batch Server**.

## Data Protection Service

---

Forcepoint DLP 8.8.1 introduces changes to the Data Protection Service.

If you have a DLP Cloud Applications license, until Forcepoint DLP 8.8.1 the incidents on DLP Cloud API and Cloud Data Discovery channels have been reported

via Data Agents. As of this version, incident reports for all cloud channels (DLP Cloud Proxy, DLP Cloud API, and Cloud Data Discovery) are reported by Data Protection Service. This is in addition to the support for DLP policy enforcement on web traffic implemented as of Forcepoint DLP 8.8.

If you are already connected to Data Protection Service, this change is transparent, and does not impact your existing setup or policies. If you are not yet connected to Data Protection Service, you must connect. Contact Forcepoint Technical Support to request your unique Data Protection Service JSON configuration file. This file should be requested prior to upgrading to DLP 8.8.1.



#### Note

To support these channels, DLP Cloud Applications must be activated. For more information, see [Forcepoint DLP 8.8.1 Administrator Help](#).

## Configuring Data Protection Service

Use the **Data Protection Service** tab of the **Settings > General > Services** page to connect to Data Protection Service. This is done by uploading tenant information from the JSON file you received from Forcepoint. Note that each time a file is uploaded, the system resets as if this is the first connection:

1. Click **Select File**, and in the dialog box that appears, click **Choose File**. Browse to the JSON file you received from Forcepoint, and then click **OK**.  
The file is uploaded to the server, and the information begins to appear in the Connection area of the Data Protection Service tab.
2. Click **Connect** to establish the connection with Data Protection Service:
3. Click **Deploy** to begin enforcing policies in cloud channels.
4. Click **OK** at the bottom of the screen to complete the process.

When the connection is active, the **Connect** button turns into a **Disconnect** button, enabling disconnection of Data Protection Service from Forcepoint DLP.

In the Data Protection Service Status area, upon successful connection, the status is marked as **Connected successfully**, the time and date of the connection is displayed, and the **Recheck connection** link is enabled. This link is used to check the connection status in the event of problems. If an error is returned upon checking the connection, the status is listed as **Failed to connect**.

After a successful connection to Data Protection Service is established, do the following to ensure the service is working properly:

1. Deploy a policy to Data Protection Service.

2. Check the incident report to make sure incidents are analyzed by Data Protection Service and not any other system component.

**Note**

As part of the integration with the Forcepoint Web Security Cloud, URL categories can now be imported from the Forcepoint Web Security Cloud Portal. See the [Forcepoint DLP Administrator Help](#) for more information.

## Error handling

- If Data Protection Service shows the status “Failed to connect”, the module is temporarily unavailable. Click **Connect** or **Recheck Connection** to try to connect again. If the problem continues, contact Forcepoint Technical Support.
- If the JSON file is uploaded for the first time, and when you click **Connect** the connection fails, the status shown is “Never connected”. This is because the Forcepoint Security Manager has never successfully connected to the Cloud Policy Engine (CPE). In this case, it is probable that a CPE was not created. Contact Forcepoint Technical Support for assistance.
- If you receive the following message in the Data Protection Service Status area:  
*This service is not connected to Forcepoint CASB. Incident reporting and policy enforcement will be affected for cloud channels. See “Explain this page” for more information.*

This means that there is a connection issue, and DLP Cloud API and Cloud Data Discovery channels will not enforce DLP policies, and the DLP Cloud Proxy channel might not report incidents to the Forcepoint Security Manager. See [Forcepoint DLP 8.8.1 Administrator Help](#), “Error handling”, for more information.

## Re-enabling fingerprint classifiers

---

A customer with a version earlier than 8.8, who already uses fingerprint classifiers and upgrades to Forcepoint DLP 8.8.1 must perform a re-activation, as explained below. Until the activation is done, only files fingerprinted after the upgrade are protected.

- To analyze structured data: Run a full scan (manually or by scheduler).
- To analyze unstructured data, you must recreate the fingerprinting database (FPNE files) as follows:
  - a. Go to the DLP installation folder %DSS\_HOME%
  - b. Run the following command to rebuild the fingerprinting database:

```
FPRUtils -o UnstructuredInsertion -Command RecreateFPNE
```



It can take about 10 minutes to rebuild the fingerprinting database depending on the size and number of fingerprints. It can also take an additional 10 minutes or so to automatically upload the fingerprints to the cloud.