



FORCEPOINT

NGFW Security Management Center Appliance

Release Notes

6.3.8

Revision A

Contents

- [About this release](#) on page 2
- [Build version](#) on page 2
- [System requirements on virtualization platforms](#) on page 3
- [Compatibility](#) on page 3
- [New features](#) on page 4
- [Enhancements](#) on page 5
- [Resolved issues](#) on page 8
- [Installation instructions](#) on page 8
- [Known issues](#) on page 10
- [Find product documentation](#) on page 10

About this release

This document contains important information about this software release for the Forcepoint NGFW Security Management Center Appliance (SMC Appliance).

We strongly recommend that you read the entire document.

The SMC Appliance ships with pre-installed Forcepoint NGFW Security Management Center (SMC) software. The pre-installed SMC includes a Management Server and a Log Server. You can alternatively install the SMC Appliance software on a virtualization platform.



Note: The SMC Appliance does not support high-availability for the Management Server or the Log Server.

Build version

SMC 6.3.8 build version is 10452.

This release contains Dynamic Update package 1088.

Product binary checksums

Use the checksums to make sure that the files downloaded correctly.

- 6.3.8U001.sap

```
SHA1SUM:
85a8dcd4fed096871f051f0fd027529d5f6713bc

SHA256SUM:
2a2c637c564ee6ed2c692fb64271b56f72a602f69f5fb31bd3aed841d2c3b83f

SHA512SUM:
9cfea31a6959a2694529f1eadde0c346
ee2c4a7f605e812fec8451af3db9a697
55642fc11b29e4377517e27ce0810c76
0b9a286419bab4ddffa6e653c89b9842
```

System requirements on virtualization platforms

We strongly recommend using a pre-installed SMC Appliance as the hardware solution. You can alternatively install the SMC Appliance software on a virtualization platform.

The following requirements apply:

- VMware ESXi version 6.0 or higher as the hypervisor
- 120 GB virtual disk minimum
- 8 GB RAM minimum
- At least one network interface



Note: The .iso installation file that is used to install the SMC Appliance software on a virtualization platform is available only for major versions of the SMC Appliance. To install the maintenance version, first install the .iso for the major version, then upgrade to the maintenance version.

Compatibility

SMC 6.3 is compatible with the following component versions.



Note: Some versions of Forcepoint NGFW might have reached end-of-life status. We recommend that you use a Long-Term Support version that is still supported. For more information about the Forcepoint NGFW lifecycle policy, see Knowledge Base article [10192](#).

SMC 6.3 can manage all compatible Forcepoint NGFW engine versions up to and including version 6.3.

- Forcepoint™ Next Generation Firewall (Forcepoint NGFW) 6.2 and 6.3
- Stonesoft® Next Generation Firewall by Forcepoint (Stonesoft NGFW) 6.0 and 6.1
- McAfee® Next Generation Firewall (McAfee NGFW) 5.7, 5.8, 5.9, and 5.10
- Stonesoft Firewall/VPN Express 5.5

- McAfee® ePolicy Orchestrator® (McAfee ePO™) 5.0.1 and 5.1.1
- McAfee® Enterprise Security Manager (McAfee ESM) 9.2.0 and later (9.1.0 CEF only)

New features

This release of the product includes these new features. For more information and configuration instructions, see the *Forcepoint Next Generation Firewall Product Guide* and the *Forcepoint Next Generation Firewall Installation Guide*.

Support for Forcepoint Endpoint Context Agent

Support for Forcepoint Endpoint Context Agent (ECA) allows you to use endpoint information in the Forcepoint NGFW policy to control access, identify users, and log their actions. ECA is a Windows client application that provides endpoint information to the NGFW Engine. ECA is a replacement for McAfee Endpoint Intelligence Agent (McAfee EIA).



CAUTION: If McAfee Endpoint Intelligence Agent (McAfee EIA) is configured on the NGFW Engine when you upgrade to version 6.3 or later, the NGFW Engine node is returned to the initial configuration state and stops processing traffic. You must remove the McAfee Endpoint Intelligence Agent (McAfee EIA) configuration and refresh the policy before you upgrade to version 6.3 or later. For more information, see Knowledge Base article [14093](#).

Multi-Layer Deployment for NGFW Engines in the Firewall/VPN role

Multi-layer deployment is now supported for NGFW Engines in the Firewall/VPN role. In multi-layer deployment, NGFW Engines in the Firewall/VPN role have both layer 2 physical interfaces and layer 3 physical interfaces. The same NGFW Engine can now provide the features of the Firewall/VPN role, as well as the inspection features of the IPS and Layer 2 Firewall roles.

Route-based VPN improvements

The user interface for configuring a route-based VPN has been improved. Instead of configuring a single Route-Based VPN element, you can create individual Route-Based VPN Tunnel elements. The route-based VPN tunnels can be used in Administrative Domains other than the Shared Domain.

Improvements in Forcepoint Advanced Malware Detection

In addition to the cloud sandbox, Forcepoint Advanced Malware Detection now also supports on-premises local sandboxes. Other improvements include the following:

- The NGFW Engine can now delay file transfers until the results of the sandbox scan are received.
- The NGFW Engine now separately requests a file reputation for each file in .zip archives.
- The reporting tools in the external portal have been improved, and it is easier to access reports in the external portal from the Management Client.

NGFW on Azure and Hyper-V

You can now deploy NGFW Engines in the Microsoft Azure cloud to provide VPN connectivity, access control, and inspection for services in the Microsoft Azure cloud. The Microsoft Hyper-V virtualization platform on Windows 2012 and 2016 servers is now also supported for NGFW deployment on a virtualization platform in a private cloud. Only NGFW Engines in the Firewall/VPN role are supported in the Microsoft Azure cloud and on the Microsoft Hyper-V virtualization platform.

Support for Forcepoint User ID Service

Forcepoint User ID Service collects information about users, groups, and IP addresses from Windows Active Directory (AD) servers and AD domains. You can use the information from the Forcepoint User ID Service in the Forcepoint NGFW policy to identify users and control access.

Support for HTTPS in Sidewinder HTTP Proxy

The Sidewinder HTTP Proxy can now provide decryption, inspection, protocol validation, certificate validation, and certificate revocation checking for the HTTPS protocol.

Enhancements

This release of the product includes these enhancements.

Enhancements in SMC version 6.3.0

Enhancement	Description
New commands for SMC Appliance	The following new subcommands of the <code>smca-system</code> command have been added: <ul style="list-style-type: none"> <code>smca-system serial-number</code> — Shows the hardware serial number for the SMC Appliance. <code>smca-system fingerprint</code> — Shows the fingerprint for the CA used by the Management Client.
Second interface on the SMC Appliance	You can now configure a second interface on the SMC Appliance when you install the appliance.
Support for serial console connections on the SMC Appliance	You can now connect to the SMC Appliance using a serial console connection, or make outbound serial console connections from the SMC Appliance to other devices, such as Forcepoint NGFW appliances.
Rate limit per Virtual NGFW Engine for traffic from the Master NGFW Engine	You can now set a rate limit per Virtual NGFW Engine for traffic from the Master NGFW Engine to the Virtual NGFW Engine. When the limit is set, a single Virtual NGFW Engine that is under very heavy load cannot disrupt the operation of the other Virtual NGFW Engines that are hosted by the Master NGFW Engine.
Dedicated control plane operation	You can now dedicate a specified number of CPUs to control plane operations. Even under very heavy loads, you can continue to manage NGFW Engines and refresh policies, and the status of the NGFW Engines remains green in the Home view.

Enhancement	Description
Changes related to certificates	<p>The NGFW Engine can now validate certificates and check the certificate revocation status for features that have certificate validation and certificate revocation checks enabled, such as features that use a TLS Profile in the configuration.</p> <p>Except for VPN certificates, most elements related to certificates are now found in the Administration > Certificates branch of the Configuration view.</p> <p>There is no longer a separate Pending Certificate Request element. Certificate requests are now created as TLS Credentials elements. The state of the TLS Credentials element indicates whether it is a signed certificate or a certificate request.</p>
Limit for half-open TCP connections	As part of the SYN flood protection feature, you can now set a limit for the number of half-open TCP connections. When the limit is reached, SYN flood protection is enabled.
Improvements to SSM architecture	Improvements to SSM integration remove some previous limitations on inspection when Sidewinder Proxies are used. These former limitations include matching traffic based on Network Applications, file filtering, and URL filtering. New Combined Protocol elements allow you to apply a standard Protocol element and a Sidewinder Proxy Protocol element to the same traffic.
New commands for managing NGFW Engines and NGFW appliances	It is now possible to power off an NGFW Engine remotely through the Management Client. In addition, you can now also reset an NGFW appliance to factory settings through the Management Client. To increase security, you can set how many times you want the stored data on the file system of the NGFW appliance to be overwritten.
Task for validating policies	There is a new task for validating policies. The Validate Policy task allows you to validate the policy installed on NGFW Engines or Master NGFW Engines or the Alert Policy installed in an administrative Domain. You can run the Validate Policy task either manually or according to a schedule.
Updated product names	The NGFW product names have been updated. Stonesoft Management Center is now called Forcepoint NGFW Security Management Center (SMC), and Stonesoft Next Generation Firewall (Stonesoft NGFW) is now called Forcepoint Next Generation Firewall (Forcepoint NGFW). The new product names are used in the SMC installer, the SMC installation directory, in the Management Client, and in the list of services in the Windows Control Panel.
Improvements in change approval process	It is now possible to give individual administrators permission to approve changes. Previously, only administrators with unrestricted permissions (superusers) could approve changes. You can also specify whether administrators are allowed to approve their own changes.
Home page improvements in the Management Client	You can now easily customize the home page for components in the Home view. You can use drag-and-drop to re-organize the panes and select new panes from a predefined selection of panes to replace existing panes on the home page. You can now include statistics in home pages. The Management Server and the Log Server now have their own home page in the Home view.

Enhancements in SMC version 6.3.2

Enhancement	Description
Java cryptography extension included for Webstart clients	The Java jurisdiction policy files that are required for Webstart Management Clients to connect to Management Servers that use 256-bit encryption are now included. Java version 1.8.0_151 is required on the computer where you use the Webstart Management Client. For more information, see Knowledge Base article 10136 .
SMC API enhancements	<ul style="list-style-type: none"> You can use SMC API read-only queries on a standby Management Server in a high availability setup. You can use SMC API queries to view the history information of an element. You can use the WebSocket protocol to view active alerts for an element.

Enhancements in SMC version 6.3.4

Enhancement	Description
TLS decryption is more visible in the Logs view	TLS traffic that is decrypted is shown in the TLS Decrypted and TLS Detected log fields in the Logs view.

Enhancements in SMC version 6.3.5

Enhancement	Description
Improved sorting of Network elements	When you sort Network elements by IP address, the elements are sorted first by IP address, then by netmask.
License reporting tool	There is a new tool for MSSP customers that exports all data related to licenses and NGFW Engines to a CSV file.

Enhancements in SMC version 6.3.6

Enhancement	Description
Delete VPN SA monitoring entries using WebSocket API	In addition to acknowledging alerts and deleting blacklist entries, it is now possible to delete entries from the VPN SA Monitoring view using the WebSocket API. For more information about the WebSocket API, see Knowledge Base article 15540 .

Resolved issues

These issues are resolved in this release of the product. For a list of issues fixed in a previous release, see the Release Notes for the specific release.

Description	Issue number
The command line tool that can be used to show or export logs on the Log Server command line, sgTextBrowser, has a 5-minute timeout. The timeout limits querying over longer time ranges.	SMC-15058
VPN validation incorrectly prevents using Multi-Link with VPN clients.	SMC-15104
Protocol parameters that are overridden in MSRPC network applications are not generated in the NGFW Engine configuration as expected.	SMC-15114

Installation instructions

Use these high-level steps to install the SMC Appliance.

For detailed information about installing the SMC Appliance and the NGFW Engines, see the *Forcepoint Next Generation Firewall Installation Guide*. All guides are available for download at <https://support.forcepoint.com>.

Steps

- 1) Turn on the SMC Appliance.
- 2) Select the keyboard layout for accessing the SMC Appliance on the command line.
- 3) Accept the EULA.
- 4) Enter the account name and password.
For credential requirements, see the *Forcepoint Next Generation Firewall Installation Guide*.
- 5) Make your security selections.
- 6) Complete the network interface and network setup fields.
- 7) Enter a host name for the Management Server.
- 8) Select the time zone.
- 9) (Optional) Configure NTP settings.
- 10) After the SMC Appliance has restarted, install the Management Client.
You can use Java Webstart or install the Management Client from a file to allow remote access to the SMC. Java Web Start is enabled by default on the Management Server that is pre-installed on the SMC Appliance.

- 11) Import the licenses for all components.
You can generate licenses at <https://stonesoftlicenses.forcepoint.com>.
- 12) Create the NGFW Engines elements, then install and configure the NGFW Engines.

Upgrade the SMC Appliance

Upgrade the SMC Appliance from a previous version to version 6.3.8.



CAUTION: Before upgrading the SMC Appliance from version 6.2.0, install the 6.2.0P001 patch. For more information, see Knowledge Base article [14168](#).

- SMC 6.3 requires an updated license.
 - If the automatic license update function is in use, the license is updated automatically.
 - If the automatic license update function is not in use, request a license upgrade on our website at <https://stonesoftlicenses.forcepoint.com>. Activate the new license using the Management Client before upgrading the software.
- The SMC Appliance must be upgraded before the engines are upgraded to the same major version.
- Upgrading is supported from SMC Appliance versions 6.2.0 – 6.3.7.

Steps

- 1) Log on to the SMC Appliance.
- 2) To check for available patches, enter the following command:

```
sudo ambr-query
```

- 3) To load the patch on the SMC Appliance, enter the following command:

```
sudo ambr-load 6.3.8U001
```

If you downloaded the patch and transferred it to the SMC Appliance, append the load command with the `-f` option and specify the full path to the patch file. Example:

```
sudo ambr-load -f /var/tmp/6.3.8U001.sap
```

- 4) To install the patch on the SMC Appliance, enter the following command:

```
sudo ambr-install 6.3.8U001
```

The installation process prompts you to continue.

- 5) Enter `Y`.

Result

The installation process restarts the appliance and installs the patch. When the upgrade is finished, the appliance restarts. The appliance is now running SMC Appliance 6.3.8.

Installing SMC Appliance patches

We recommend checking the availability of SMC Appliance patches regularly, and installing the patches when they become available.

The SMC Appliance patches can include improvements and enhancements to the SMC software, the operating system, or the SMC Appliance hardware.

For detailed information about installing SMC Appliance patches, see the *Forcepoint Next Generation Firewall Installation Guide*. All guides are available for download at <https://support.forcepoint.com>.

Known issues

For a list of known issues in this product release, see Knowledge Base article [14117](#).

Find product documentation

On the Forcepoint support website, you can find information about a released product, including product documentation, technical articles, and more.

You can get additional information and support for your product on the Forcepoint support website at <https://support.forcepoint.com>. There, you can access product documentation, Knowledge Base articles, downloads, cases, and contact information.

Product documentation

Every Forcepoint product has a comprehensive set of documentation.

- *Forcepoint Next Generation Firewall Product Guide*
- Forcepoint Next Generation Firewall online Help



Note: By default, the online Help is used from the Forcepoint help server. If you want to use the online Help from a local machine (for example, an intranet server or your own computer), see Knowledge Base article [10097](#).

- *Forcepoint Next Generation Firewall Installation Guide*

Other available documents include:

- *Forcepoint Next Generation Firewall Hardware Guide* for your model
- *Forcepoint NGFW Security Management Center Appliance Hardware Guide*
- *Forcepoint Next Generation Firewall Quick Start Guide*
- *Forcepoint NGFW Security Management Center Appliance Quick Start Guide*
- *Forcepoint NGFW SMC API Reference Guide*
- *Stonesoft VPN Client User Guide* for Windows or Mac
- *Stonesoft VPN Client Product Guide*

