



FORCEPOINT

Next Generation Firewall

Release Notes

5.10.14

Revision A

Contents

- [About this release](#) on page 2
- [Lifecycle model](#) on page 2
- [System requirements](#) on page 3
- [Build version](#) on page 6
- [Compatibility](#) on page 7
- [New features](#) on page 7
- [Enhancements](#) on page 9
- [Resolved issues](#) on page 10
- [Installation instructions](#) on page 11
- [Known issues](#) on page 12
- [Find product documentation](#) on page 12

About this release

This document contains important information about this release of Forcepoint™ Next Generation Firewall (Forcepoint NGFW; formerly known as McAfee® Next Generation Firewall). We strongly recommend that you read the entire document.

NGFW version 5.10.1 has been evaluated against the Common Criteria Network Devices Protection Profile with Extended Package Stateful Traffic Filter Firewall. For more details, see <https://www.niap-ccevs.org/Product/Compliant.cfm?pid=10669>.



Note: We have started rebranding the NGFW product and the NGFW product documentation. We use Stonesoft as the product name in this document. However, the old product name is still used in the NGFW appliances and the product documentation set that we created for the NGFW 5.10.0 release.

Lifecycle model

This release of Forcepoint NGFW is a Long-Term Support (LTS) version.

We recommend using the most recent Long-Term Support (LTS) version if you do not need any features from a later Feature Stream version.

For more information about the Forcepoint NGFW lifecycle policy, see Knowledge Base article [10192](#).

System requirements

Make sure that you meet these basic hardware and software requirements.

Forcepoint NGFW appliances

We strongly recommend using a pre-installed Forcepoint NGFW appliance as the hardware solution for new Forcepoint NGFW installations.



Note: Some features in this release are not available for all appliance models. See Knowledge Base article [9743](#) for up-to-date appliance-specific software compatibility information.

Two Forcepoint NGFW engine images are available:

- x86-64 — A 64-bit image that includes the Local Manager.
- x86-64-small — A 64-bit image that does not include the Local Manager.



Note: If you do not use the Local Manager, we recommend that you use the x86-64-small image. Some appliance models support only the x86-64-small image.

The following table shows whether you can use an appliance model in the Firewall/VPN (FW), IPS, or Layer 2 Firewall (L2FW) role, and the image that is supported.

Appliance model	Roles	Images
FW-315	FW	The image that does not include the Local Manager is supported
320X (MIL-320)	FW	Both images are supported
IPS-1205	IPS, L2FW	Both images are supported
FWL321	FW	The image that does not include the Local Manager is supported
NGF321	FW, IPS, L2FW	Both images are supported
FWL325	FW	The image that does not include the Local Manager is supported
NGF325	FW, IPS, L2FW	Both images are supported
110	FW	The image that does not include the Local Manager is supported
1035	FW, IPS, L2FW	Both images are supported
1065	FW, IPS, L2FW	Both images are supported
1101	FW, IPS, L2FW	Both images are supported
1105	FW, IPS, L2FW	Both images are supported
1301	FW, IPS, L2FW	Both images are supported
1302	FW, IPS, L2FW	Both images are supported
1401	FW, IPS, L2FW	Both images are supported
1402	FW, IPS, L2FW	Both images are supported

Appliance model	Roles	Images
2101	FW, IPS, L2FW	Both images are supported
2105	FW, IPS, L2FW	Both images are supported
3201	FW, IPS, L2FW	Both images are supported
3202	FW, IPS, L2FW	Both images are supported
3205	FW, IPS, L2FW	Both images are supported
3206	FW, IPS, L2FW	Both images are supported
3207	FW, IPS, L2FW	Both images are supported
3301	FW, IPS, L2FW	Both images are supported
3305	FW, IPS, L2FW	Both images are supported
5201	FW, IPS, L2FW	Both images are supported
5205	FW, IPS, L2FW	Both images are supported
5206	FW, IPS, L2FW	Both images are supported
6205	FW, IPS, L2FW	Both images are supported

Sidewinder S-series appliances

These Sidewinder appliance models can be re-imaged to run Forcepoint NGFW software.

Appliance model	Roles	Images
S-1104	FW	Both images are supported
S-2008	FW	Both images are supported
S-3008	FW	Both images are supported
S-4016	FW	Both images are supported
S-5032	FW	Both images are supported
S-6032	FW	Both images are supported

Certified Intel platforms

We have certified specific Intel-based platforms for Forcepoint NGFW.

The tested platforms can be found at <https://support.forcepoint.com> under the Forcepoint Next Generation Firewall product.

We strongly recommend using certified hardware or a pre-installed Forcepoint NGFW appliance as the hardware solution for new Forcepoint NGFW installations. If it is not possible to use a certified platform, Forcepoint NGFW can also run on standard Intel-based hardware that fulfills the hardware requirements.

Basic hardware requirements

You can install Forcepoint NGFW on standard hardware with these basic requirements.

- (Recommended for new deployments) Intel® Xeon®-based hardware from the E5-16xx product family or higher



Note: Legacy deployments with Intel® Core™2 are supported.

- IDE hard disk and CD drive



Note: IDE RAID controllers are not supported.

- Memory:
 - 4 GB RAM minimum for x86-64-small installation
 - 8 GB RAM minimum for x86-64 installation
- VGA-compatible display and keyboard
- One or more certified network interfaces for the Firewall/VPN role
- Two or more certified network interfaces for IPS with IDS configuration
- Three or more certified network interfaces for Inline IPS or Layer 2 Firewall

For information about certified network interfaces, see Knowledge Base article [9721](#).

Master NGFW Engine requirements

Master Engines have specific hardware requirements.

- Each Master NGFW Engine must run on a separate physical device. For more details, see the *Forcepoint Next Generation Firewall Installation Guide*.
- All Virtual NGFW Engines hosted by a Master NGFW Engine or Master NGFW Engine cluster must have the same role and the same Failure Mode (*fail-open* or *fail-close*).
- Master NGFW Engines can allocate VLANs or interfaces to Virtual Security Engines. If the Failure Mode of the Virtual IPS engines or Virtual Layer 2 Firewalls is *Normal* (fail-close) and you want to allocate VLANs to several engines, you must use the Master NGFW Engine cluster in standby mode.
- Cabling requirements for Master NGFW Engine clusters that host Virtual IPS engines or Layer 2 Firewalls:
 - Failure Mode *Bypass* (fail-open) requires IPS serial cluster cabling.
 - Failure Mode *Normal* (fail-close) requires Layer 2 Firewall cluster cabling.

For more information about cabling, see the *Forcepoint Next Generation Firewall Installation Guide*.

Virtual appliance node requirements

You can install Forcepoint NGFW on virtual appliances with these hardware requirements. Also be aware of some limitations.

- (Recommended for new deployments) Intel® Xeon®-based hardware from the E5-16xx product family or higher



Note: Legacy deployments with Intel® Core™2 are supported.

- One of the following hypervisors:
 - VMware ESXi 5.5 and 6.0



Note: Forcepoint Next Generation Firewall 5.10.14 does not support integration with Intel Security Controller and deployment on VMware NSX.

- KVM (KVM is tested as shipped with Red Hat Enterprise Linux Server 7.0)
- Oracle VM server 3.3 (tested with Oracle VM server 3.3.1)
- 8 GB virtual disk
- 4 GB RAM minimum
- A minimum of one virtual network interface for the Firewall/VPN role, three for IPS or Layer 2 Firewall roles

When Forcepoint NGFW is run as a virtual appliance node in the Firewall/VPN role, these limitations apply:

- Only Packet Dispatching CVI mode is supported.
- Only standby clustering mode is supported.
- Heartbeat requires a dedicated non-VLAN-tagged interface.

When Forcepoint NGFW is run as a virtual appliance node in the IPS or Layer 2 Firewall role, clustering is not supported.

Build version

Forcepoint Next Generation Firewall 5.10.14 build version is 14126.

Product binary checksums

Use the checksums to make sure that the installation files downloaded correctly.

- `sg_engine_5.10.14.14126_x86-64.iso`

```
SHA1SUM:
821accdf2b79244a737c87a58c521f15dbbf2bcd

SHA256SUM:
817b6d2905a9d0dc94f2f8f04f267f6f1747190d0ebe55538b79dba19cce0f26

SHA512SUM:
3b18dfd33c5f51587e2c9a4a5bccbba5
33ea1a1058ec1622f42e3230b19a52a2
9a2c3d43909f1c94bcac9aa9891be059
1a8d77a6ca6f23dd27ba9aae7cabc3f7
```

- `sg_engine_5.10.14.14126_x86-64.zip`

```
SHA1SUM:
db335ada2e525b2763fc2708130fca4c15d39e06

SHA256SUM:
2c5c4d9e8d7b9af8b66d127b8136ba19a107c573679b87d39f88f1dbe1c49262

SHA512SUM:
e0d007864e93a4c48783fd3b6401064b
19e1470dcb00aaf0673c0e6090cdca35
0c2c6a24f1c0c9374d86ea9dcc4d798f
b3f57200c0e6c8bf7b076437b79286e1
```

- `sg_engine_5.10.14.14126_x86-64-small.iso`

```
SHA1SUM:  
79b834d852092b9b04f10f9f97b77c88f61ce00c  
  
SHA256SUM:  
cc793316d777a275652ab7b9feb19ccc2ef9e7b4abca3ac22b87f24c63d1b642  
  
SHA512SUM:  
0f1218ed0dad6d7a9847ff209b5df734  
1627b2f306415b9015915fd1ba2eec5e  
d2af54e82d7985bc8e3dace957687b5b  
a93c4b90e46f029a02dc5afbe159a18d
```

- `sg_engine_5.10.14.14126_x86-64-small.zip`

```
SHA1SUM:  
640880fe0c894f388090767c0be156534c337187  
  
SHA256SUM:  
067104a21d5a000a71a622a2b02987427dc344ac5db2a73a93a4304352e40a4d  
  
SHA512SUM:  
1641ea4bb7bc68644b5c00c8552b7176  
3cacff11f4bacf5a1a7e1add5984d657  
15cb4f3501ef60aabda24c6aec149894  
5a2a46208ec45a220a518b19add408ee
```

Compatibility

Forcepoint NGFW 5.10.14 is compatible with the following component versions.

- Forcepoint NGFW Security Management Center (SMC) (formerly known as McAfee® Security Management Center) 5.10.0 or later
- Dynamic Update 810 or later
- Stonesoft IPsec VPN Client 5.3.0 or later
- Stonesoft® VPN Client (formerly known as McAfee® VPN Client for Windows) 5.9.0 or later
- Stonesoft® VPN Client for Mac OS X (formerly known as McAfee® VPN Client for Mac OS X) 1.0.0 or later
- Stonesoft® VPN Client for Android (formerly known as McAfee® VPN Client for Android) 1.0.1 or later
- Server Pool Monitoring Agent 4.0.0 or later
- McAfee® Logon Collector 2.2 and 3.0
- McAfee® Advanced Threat Defense 3.6
- McAfee Endpoint Intelligence Agent (McAfee EIA) 2.5

New features

This release of the product includes these new features. For more information and configuration instructions, see the *Forcepoint Next Generation Firewall Product Guide*.



Note: Forcepoint Next Generation Firewall 5.10.14 does not support integration with Intel Security Controller and deployment on VMware NSX.

Support for Threat Intelligence Exchange

Forcepoint NGFW can now query file reputations and receive reputation updates from the McAfee® Threat Intelligence Exchange (TIE) server. TIE makes it possible for administrators to tailor comprehensive local threat intelligence from global intelligence data sources, such as McAfee® Global Threat Intelligence™ (McAfee GTI), endpoints, gateways, and other security components. File reputation data is exchanged using the McAfee® Data Exchange Layer (DXL) broker network. File reputation updates ensure that Forcepoint NGFW engines always have the latest file reputations available for use in file filtering.

Single sign-on (SSO) to SSL VPN Portal

The SSL VPN Portal (reverse web proxy) can be configured to cache user credentials. The portal logs on to the back-end servers with the credentials as if they came from the web browser at the endpoint. You can group the servers that use the same credentials by SSO domain, to further reduce the need to re-enter the password.

New tunnel type for the route-based VPN

A new tunnel type for the route-based VPN allows the use of tunnel mode IPsec without an additional tunneling layer. The route-based VPN configuration dialog box has been improved.

Connectivity between Forcepoint NGFW and SMC using IPv6

Engines that only use IPv6 to connect to the Internet can now be managed by SMC over the Internet using IPv6-based management connections. Connectivity between SMC components still requires IPv4 addressing and connectivity.

Network Security for Industrial Control Systems (ICS)

ICS support has been enhanced with deep inspection support for DNP3 (TCP/UDP) and Open Platform Communications Unified Architecture (OPC UA).

Safe search support

Forcepoint NGFW can be configured to enforce safe search usage for Google, Bing, Yahoo, and DuckDuckGo web searches.

Enhancements

This release of the product includes these enhancements.

Enhancements in Forcepoint NGFW version 5.10

Enhancement	Description
Advanced Threat Defense communication logging improvements	Improvements have been made to the communication protocol and logging features between McAfee® Advanced Threat Defense and Forcepoint NGFW. Forcepoint NGFW now logs the dynamic analysis results when available from Advanced Threat Defense. Forcepoint NGFW provides the file name, destination IP address, and URL details when sending the file to Advanced Threat Defense for analysis.
File filtering improvements	Improvements have been made to file type detection and filtering. We recommend that you update your file filtering policies with the new file type categories.
DHCP services	It is now possible to use DHCP server and DHCP relay services on different interfaces of the same Forcepoint NGFW engine.

Enhancements in Forcepoint NGFW version 5.10.3

Enhancement	Description
Dynamic routing enhancements	Dynamic routing features, such as graceful restart for OSPF and BGP, have been improved. The stability of dynamic routing has also been improved.

Enhancements in Forcepoint NGFW version 5.10.4

Enhancement	Description
Improved alerting for offline transitions	Alerting for offline transitions has been improved. Alerts are now created for unexpected offline transitions, such as heartbeat recovery, or nodes that have different policies.
Faster policy installation for Virtual Security Engines	Policy installation is now faster in environments that have many Virtual Security Engines.

Enhancements in Forcepoint NGFW version 5.10.8

Enhancement	Description
Engine monitoring enhancements	Engine monitoring has been improved. If the monitoring connection through a primary Control Interface fails, the backup Control Interface is used.

Enhancement	Description
Improved logging for File Filtering	Logging for File Filtering has been improved significantly. For example, all File Filtering Situations are now logged under File Filtering in the Facility column of the Logs view.
Inspection with a larger number of Virtual Security Engines	Inspection can now be used with a larger number of Virtual Security Engines that are hosted on a single Master Engine.

Enhancements in Forcepoint NGFW version 5.10.14

Enhancement	Description
IGMP-based multicast forwarding enhancement	When an NGFW Engine is used as an IGMP proxy for multicast forwarding, the number of supported multicast groups has increased.

Resolved issues

These issues are resolved in this release of the product. For a list of issues fixed in earlier releases, see the Release Notes for the specific release.

Description	Role	Issue number
If an NGFW Engine is selected in the Home view of the Management Client, the memory consumption of the selected node might start to increase while the Home view remains open. The memory is released when you close the Management Client.	FW, IPS, L2FW	NGFW-7303
When an HTTP Protocol Agent has URL logging enabled, but the Access rule does not have deep inspection enabled, the URL is not logged.	FW, IPS, L2FW	NGFW-8537
Refreshing the policy on a Virtual NGFW Engine that has active VPN connections might cause the Master NGFW Engine and its hosted Virtual NGFW Engines to stop processing traffic. You must restart the Master NGFW Engine to start processing traffic again.	FW	NGFW-8680
You cannot use the NGFW Initial Configuration Wizard (sg-reconfigure) in a web browser with 2100 series NGFW appliances.	FW, IPS, L2FW	NGFW-8683
IPsec tunnels through a standby endpoint might be negotiated unnecessarily.	FW	NGFW-8774
In a route-based VPN tunnel which is of the type GRE, IP-IP, or SIT, traffic might stop being processed after the policy is refreshed.	FW	NGFW-8786
If an external IGMP proxy is configured to use IGMP version 3 and an NGFW Engine IGMP proxy is configured to use IGMP version 2, multicast traffic might not be forwarded successfully.	FW	NGFW-8875

Installation instructions

Use these high-level steps to install SMC and the Forcepoint NGFW engines.

For detailed information, see the *Forcepoint Next Generation Firewall Installation Guide*. All guides are available for download at <https://support.forcepoint.com>.



Note: The sgadmin user is reserved for SMC use on Linux, so it must not exist before SMC is installed for the first time.

Steps

- 1) Install the Management Server, the Log Servers, and optionally the Web Portal Servers.
- 2) Import the licenses for all components.
You can generate licenses at <https://stonesoftlicenses.forcepoint.com>.
- 3) Configure the Firewall, IPS, or Layer 2 Firewall elements with the Management Client using the **Security Engine Configuration** view.
- 4) To generate initial configurations for the engines, right-click each Firewall, IPS, or Layer 2 Firewall element, then select **Configuration > Save Initial Configuration**.
Make a note of the one-time password.
- 5) Make the initial connection from the engines to the Management Server, then enter the one-time password.
- 6) Create and upload a policy on the engines using the Management Client.

Upgrade instructions

Take the following into consideration before upgrading licenses, engines, and clusters.

- Upgrading to version 5.10.x is only supported from version 5.8.x or later. If you have an earlier version, first upgrade to the latest 5.8.x version.
- Forcepoint NGFW 5.10.x requires an updated license if upgrading from version 5.9.x or earlier. The license upgrade can be requested at <https://stonesoftlicenses.forcepoint.com>. Install the new license using the Management Client before upgrading the software. If communication between the SMC and the license server is enabled and the maintenance contract is valid, the license is updated automatically.
- To upgrade the engine, use the remote upgrade feature or reboot from the installation CD and follow the instructions. For detailed instructions, see the *Forcepoint Next Generation Firewall Installation Guide*.

Take the following software architecture information into consideration.

- Forcepoint NGFW appliances support only the software architecture version with which they come installed. 32-bit versions (i386) can only be upgraded to another 32-bit version and 64-bit versions (x86-64) can only be upgraded to another 64-bit version.
- Clusters can only have online nodes that use the same software architecture version.
- State synchronization between 32-bit and 64-bit versions is not supported.
- Changing the architecture of third-party servers using software licenses requires the software to be fully re-installed from a CD.

- Forcepoint NGFW version 5.10 only supports 64-bit software architecture. Except for the FW-315 appliance, the last supported software version for 32-bit Firewall/VPN appliances is 5.8.
- To upgrade a cluster (consisting of FW-315 appliances or third-party hardware using software licenses) from a 32-bit to 64-bit version, see Knowledge Base article [9875](#).

Known issues

For a list of known issues in this product release, see Knowledge Base article [10138](#).

Known limitations

This release of the product includes these known limitations.

Limitation	Description
Inspection in asymmetrically routed networks	In asymmetrically routed networks, using the stream-modifying features (TLS Inspection, URL filtering, and file filtering) can make connections stall.
SSL/TLS inspection in capture (IDS) mode	Due to SSL/TLS protocol security features, SSL/TLS decryption in capture (IDS) mode can only be applied in a server protection scenario when RSA key exchange negotiation is used between the client and the server.
Inline Interface disconnect mode in the IPS role	The <i>disconnect mode</i> for Inline Interfaces is not supported on IPS virtual appliances, IPS software installations, IPS appliance models other than IPS-6xxx, or modular appliance models that have bypass interface modules.

Find product documentation

On the Forcepoint support website, you can find information about a released product, including product documentation, technical articles, and more.

You can get additional information and support for your product on the Forcepoint support website at <https://support.forcepoint.com>. There, you can access product documentation, Knowledge Base articles, downloads, cases, and contact information.

Product documentation

Every Forcepoint product has a comprehensive set of documentation.

- Stonesoft Next Generation Firewall Product Guide*
- Stonesoft Next Generation Firewall online Help



Note: By default, the online Help is used from the Forcepoint help server. If you want to use the online Help from a local machine (for example, an intranet server or your own computer), see Knowledge Base article [10097](#).

- Stonesoft Next Generation Firewall Installation Guide*

Other available documents include:

- *Stonesoft Next Generation Firewall Hardware Guide* for your model
- *Stonesoft Next Generation Firewall Quick Start Guide*
- *Stonesoft SMC API Reference Guide*
- *Stonesoft VPN Client User Guide* for Windows or Mac
- *Stonesoft VPN Client Product Guide*

